

## Install a SmartReport virtual appliance



This document contains confidential information and must not be communicated to third parties without the written permission of Acipia.

Reference  
**Install a SmartReport virtual appliance**

Author :  
Version : 1.0

**Acipia**

☎ 03 20 28 61 62

📠 03 20 70 57 11

50 avenue Jean Lebas  
59 100 Roubaix



## Summary

<b>Presentation of the document.....</b>	<b>3</b>
Document management.....	3
<b>How to import SmartReport.....</b>	<b>4</b>
<b>How to configure the appliance.....</b>	<b>8</b>



## PRESENTATION OF THE DOCUMENT

This document describes the procedure for deploying a SmartReport virtual appliance on a VMware hypervisor. This procedure mainly consists in importing an OVA image to the hypervisor.

### Document management


Revision			
Version	Date	Author	Comments
1.0	12/11/2012	A. S.	Initial version

# HOW TO IMPORT SMARTREPORT

To import SmartReport, start vSphere Client.


Once it is launched, go to the « File » menu and click on « Deploy OVF Template... » as shown in *figure n°1*.

**Figure n°1**




Click on « Browse » (*Figure n°2*), select the OVA file of SmartReport then validate by clicking on the « Next » button.

**Figure n°2**




A window summarising the information of the SmartReport VM opens (*Figure n°3*). Validate by clicking on « Next » as illustrated in the figure.

**Figure n°3**



The next window allows you to modify the VM name, if you wish, although it is not necessary. You can therefore directly validate by clicking on « Next » (*Figure n°4*).


**Figure n°4**






Check the box saying « Thick provisioned format » to immediately allocate to the VM all the disk space needed (*Figure n°5*).

**Figure n°5**



Then click on « Finish » to start importing the VM (*Figure n°6*).


**Figure n°6**






*Figure n°7* and *figure n°8* show the importation progress of the VM's disk 1 then disk 2, and *figure n°9* shows the message informing you that the importation was successful. Click on « Close » to finish the importation.


***Figure n°7***



***Figure n°8***



***Figure n°9***





## HOW TO CONFIGURE THE APPLIANCE

Once you have imported the SmartReport appliance, you will have to configure it. In order to do that, please refer to SmartReport's Userguide, Chapter 2, section ***"Initial configuration of a SmartReport appliance"***.